



OptoFidelity Touch and Test Python Client Reference

1 Getting started

TnT python client has been tested with python 3.5 in 32-bit Windows, 64-bit Windows, 32-bit MacOS, and 64-bit MacOS environments.

To get started, make sure that TnT Server is running. Then import TnTClient module and create an instance of TnTRobotClient or TnTDUTClient class.

To control robot in robot workspace frame, create an instance of TnTRobotClient class. TnTClient class implements some factory methods to help creating other robot control classes such as TnTRobotClient.

Example:

```
from tntclient.tnt_client import TnTClient
client = TnTClient()
robot = client.robot("Robot1")
robot.move(20.0, 20.0, 10.0) # example command
```

To control robots and actuators in DUT coordinate frame, create an instance of class TnTDUTClient. This can be done by first creating TnTClient object with required initialization and then by creating TnTDUTClient.

Example:

```
from tntclient.tnt_client import TnTClient
tntclient = TnTClient()
robot = tntclient.robot("Robot1")
dut = tntclient.dut("DUT1")
dut.robot = robot
dut.jump(x=20.0, y=20.0, z=10.0, jump_height=40.0) # example command
```

More examples can be found under examples/ directory in the TnT Client package.

2 Units

In function parameters, following units are assumed unless otherwise stated:

- Linear length: millimeters [mm]
- Angle: degrees [deg]
- Time: seconds [s]
- Mass: grams [g]

Such parameters are represented with floating point types so that decimal values are allowed.

3 Module: tnt_audio_analyzer_client

3.1 Class: TnTAudioAnalyzerClient

Analyzer for analyzing audio signals.

Method: find_frequency_peaks

Description:

Find frequency peaks in given time-domain audio sampling.

Arguments:

value	sound in wav formatted bytes (same as NodeMicrophone format). (The name of this parameter is dictated by client REST api functions and cannot be refactored)
-------	--

Returns:

a list containing a list of frequencies (Hz) and a list of corresponding spectral intensities.

4 Module: tnt_camera_client

4.1 Class: TnTCameraClient

TnT™ Compatible Camera resource Should work together with - TnT Sequencer - TnT Positioning Tool - TnT UI

Camera coordinate convention: Camera node's parent frame determines the camera mount frame. Convention is that camera mount frame local z-axis points in the direction of the camera view (towards imaging target). When looking along camera view, the local x-axis of camera mount frame points to the left meaning that the pixel x-coordinates increase along negative local x-axis direction. The local y-axis direction points down in the image meaning that pixel y-coordinates increase along positive local y-axis direction.

Method: detect_icon

Description:

DEPRECATED! List of detected objects with their positions in relation to given context.

Arguments:

icon	Name of the icon. You can teach new icons with TnT UI.
confidence	Confidence factor 0..1 where 1 is very confident. Normal confidence is about 0.7.
context	Returned positions are relative to this context.
detector	Detector name as string, like "halcon".
exposure	Exposure in seconds. If not set, uses last exposure used.
gain	Gain value. If not set, uses last gain value used.

Returns:

List of detected objects.

Method: focus_height

Description:

Get camera focus height (distance)

Arguments:

None

Returns:

Focus height in mm.

Method: get_parameter

Description:

Get parameter value.

Arguments:

name	Name of the parameter to be read.
------	-----------------------------------

Returns:

{'status': 'ok', 'params': parameter_dictionary}.

Method: get_parameters

Description:

Get given set of parameters from camera. Input dict indicates which parameters are retrieved.

Arguments:

parameters	Additional arguments to indicate which parameters should be retrieved from camera. Values are ignored. List cannot be passed into HTTP GET that only has arguments and no body.
------------	---

Returns:

Dictionary of requested parameters and their values.

Method: `read_text`

Description:

DEPRECATED! Take a photo and analyze the image for text.

Arguments:

context	Returned positions are relative to this context.
language	Language as string, like "English" (default).
detector	Analyzer name, like abbyy (default).
exposure	Exposure in seconds. If not set, uses last exposure used.
gain	Gain value. If not set, uses last gain value used.
parameters	Additional parameters for the OCR engine.

Returns:

Found text with position information.

Method: `take_still`

Description:

Takes a photo. This function opens camera automatically, no need to use open() -function. In case the still is taken in the middle of stream view, a sleep-command might be needed before taking still to ensure that all the images from continuous capture are processed before clearing the queue.

Arguments:

filetype	jpg, png, raw(np.array).
width	optional target image width. both width and height needed
height	optional target image height. both width and height needed
zoom	optional image zoom.
undistorted	true/false, only available after undistort called succesfully
exposure	exposure in seconds. If not set, uses last exposure used.
gain	gain value. If not set, uses last gain value used.
scaling	Camera image scaling factor in range [0, 1].
interpolation	Interpolation method ('nearest', 'linear', 'cubic').
flipx	mirror x-coordinates of the image
flipy	mirror y-coordinages of the image
rotate90	rotate the image 90 degrees
duration	Video capture duration in seconds. Per-pixel maximum will be taken over the video.

Returns:

image in 'filetype' format In case filetype is "bytes", the returned image is bytearray that can be transformed into numpy array as:
data = camera_client.take_still(filetype="bytes") w = int.from_bytes(data[0:4], byteorder="big") h = int.from_bytes(data[4:8], byteorder="big") d = int.from_bytes(data[8:12], byteorder="big") data = np.frombuffer(data[12:], dtype=np.uint8).reshape((h, w, d))

Method: `screenshot`

Description:

Take a still image with camera and store as image object.

Arguments:

crop_left	Left coordinate for cropping rectangle. If None then 0 is used.
crop_upper	Upper coordinate for cropping rectangle. If None then 0 is used.
crop_right	Right coordinate for cropping rectangle. If None then maximum value is used.
crop_lower	Lower coordinate for cropping rectangle. If None then maximum value is used.
crop_unit	Unit of crop coordinates One of "per", "pix" or "mm".
exposure	exposure in seconds. If not set, uses last exposure used.
gain	gain value. If not set, uses last gain value used.
duration	Video capture duration in seconds. Per-pixel maximum will be taken over the video.

Returns:

Image name.

Method: close

Description:

Shuts down the camera.

Arguments:

None

Method: move

Description:

Move camera focus point to given position (x, y, and z-coordinate) in a given context.

Arguments:

x	Target x coordinate in a given context.
y	Target y coordinate in a given context.
z	Target z coordinate in a given context.
context	Name of the target context.

Method: open

Description:

Open camera for use. After the camera has been opened, sequential images can be taken quickly.

Arguments:

None

Method: set_parameter

Description:

Set parameter value.

Arguments:

name	Name of the parameter to set.
value	Value to set to the parameter.

Returns:

{'status': 'ok'}

Method: set_parameters

Description:

Set camera parameters. See get_parameters.

Arguments:

parameters	Parameter dictionary.
------------	-----------------------

Returns:

```
{'status': 'ok'}
```

Method: `start_continuous`

Description:

Start continuous camera image capture. Note that Camera node argument `max_queue_size` should be small such as 1 to avoid latency.

The mjpeg stream can be retrieved via GET request at URL

`http://127.0.0.1:8000/tnt/workspaces/ws/cameras/Camera1/mjpeg_stream` where Camera1 is the name of the camera node.

This can be used in HTML image element to view the stream. Be aware that browser can cache the image so if may be necessary to add e.g. current time as parameter to the URL by importing time library and adding `'?'+str(time.time())` to the URL

Arguments:

width	Width of image or None to use full image width.
height	Height of image or None to use full image width.
zoom	Zoom factor or None for no zoom.
undistorted	Use distortion calibration to undistort?
exposure	Camera exposure or None to use Camera node exposure state.
gain	Camera gain or None to use Camera node exposure state.
scaling	Scaling factor or None for no scaling.
interpolation	Interpolation method ("nearest", "linear" or "cubic"). May affect image stream performance.
trigger_type	Camera triggering based on internal timer "SW" or external trigger "HW".
target_context	Possible DUT target for image context transformation, "None" means no transformation. (Default: None)
target_context_margin	Margin for context transformation. (Default: 0)

Method: `stop_continuous`

Description:

Stop continuous capture that was started by `start_continuous()`.

Arguments:

None

5 Module: tnt_dut_client

5.1 Class: TnTDUTClient

TnT™ Compatible DUT resource Should work together with - TnT Sequencer - TnT Positioning Tool

Method: info

Description:
Read raw info from DUT device

Arguments:
None

Returns:
info dictionary

Method: list_buttons

Description:
List button names of the current DUT.

Arguments:
None

Returns:
List of button names.

Method: region_contour

Description:
Return the given region as a list of (x, y) points. "contour" as in how OpenCV names the approximation of a shape as a point list: 'Contours can be explained simply as a curve joining all the continuous points (along the boundary)' Can be used to OpenCV shape analysis or any other shape-analysis or geometric operation.

Arguments:

region	Name of the region.
num_points	Number of points to use on contour.

Returns:
List of (x, y) contour points, in millimeters. Scaling is applied.

Method: get_robot_position

Description:
Get the current robot position in DUT coordinates. DEPRECATED: Added for client compatibility.

Arguments:

robot_name	Name of robot whose position to get.
------------	--------------------------------------

Returns:
Robot position in DUT coordinates.

Method: svg_data

Description:
Return the svg file specified for the dut. If there is no specified file, return empty string

Arguments:
None

Returns:
svg file or empty string

Method: touches

Description:

Gets list of touches since last call of this function. If you want to clear the touches buffer, call this function and discard the results.

Current OptoTouch application supports the following fields: x Touch x-coordinate. Touch resolution is the same as screen pixel resolution. y Touch y-coordinate. Touch resolution is the same as screen pixel resolution. pressure Touch pressure, float value in range 0..1, device dependent and not any standard unit. id Touch id. Sequential number where every new finger to touch the screen takes the first free positive number as id. action Numbered enumeration where: 0 = touch start 1 = touch end 2 = touch move / stays pressed at point 3 = touch cancelled orientation Stylus event; angle in radians where 0 == north, -pi/2 = west, pi/2 = east azimuth Stylus event; angle in radians where 0 == normal to surface and M_PI/2 is flat to surface. distance Stylus event; 0.0 indicates direct contact and larger values indicate increasing distance from the surface.

Arguments:

None

Returns:

(dict) where key 'fields' is a list of touch field names. and where key 'touches' is a list of touches. One touch is an array of values.

Method: find_objects

Description:

Find an object model (.shm) from the currently visible portion of the screen.

Arguments:

filename	Name of the icon. This is the same as the icon filename without extension.
min_score	Minimum accepted confidence score of result [0.0 .. 1.0] (default 0.8).
crop_left	Left coordinate for cropping rectangle. If None then 0 is used.
crop_upper	Upper coordinate for cropping rectangle. If None then 0 is used.
crop_right	Right coordinate for cropping rectangle. If None then maximum value is used.
crop_lower	Lower coordinate for cropping rectangle. If None then maximum value is used.
crop_unit	Unit of crop coordinates One of "per", "pix" or "mm".
exposure	Exposure in seconds. If not set, uses last exposure used.
gain	Gain value. If not set, uses last gain value used.
detector	detector node to be used in object recognition
offset_x	Take the picture with an offset in x from the DUT display center. (default is 0)
offset_y	Take the picture with an offset in y from the DUT display center. (default is 0)
camera_id	Name of the camera that is being used. (default is Camera1)
duration	Video capture duration in seconds. Per-pixel maximum is taken over the video frames. If set to None only one screenshot is taken.
parameters	Optional detection parameters to override default values.

Returns:

Dictionary with keys: "success", "screenshot", "results". Response body: success -- Always True results -- Array of Result objects screenshot -- Name of the screenshot Result object (dictionary): score -- Match score [0.0 .. 1.0] topLeftX_px -- Bounding box top left x coordinate in pixels topLeftY_px -- Bounding box top left y coordinate in pixels bottomRightX_px -- Bounding box bottom right x coordinate in pixels bottomRightY_px -- Bounding box bottom right y coordinate in pixels centerX_px -- Bounding box center x coordinate in pixels centerY_px -- Bounding box center y coordinate in pixels topLeftX -- Bounding box top left x coordinate in mm topLeftY -- Bounding box top left y coordinate in mm bottomRightX -- Bounding box bottom right x coordinate in mm bottomRightY -- Bounding box bottom right y coordinate in mm centerX -- Bounding box center x coordinate in mm centerY -- Bounding box center y coordinate in mm shape -- Name of the shape file scale -- Detected icon scale angle -- Detected icon angle

Method: screenshot

Description:

Take screenshot of DUT screen and save it as image. First moves robot so that camera is in the middle of the DUT.

Arguments:

camera_id	Name of camera to take image with.
crop_left	Left coordinate for cropping rectangle. If None then 0 is used.
crop_upper	Upper coordinate for cropping rectangle. If None then 0 is used.
crop_right	Right coordinate for cropping rectangle. If None then maximum value is used.
crop_lower	Lower coordinate for cropping rectangle. If None then maximum value is used.
crop_unit	Unit of crop coordinates One of "per", "pix" or "mm".
exposure	exposure in seconds. If not set, uses last exposure used.
gain	gain value. If not set, uses last gain value used.
offset_x	Take the picture with an offset in x from the DUT display center. (default is 0)
offset_y	Take the picture with an offset in y from the DUT display center. (default is 0)

Returns:

Image name.

Method: `search_text`

Description:

Search text pattern from the visible portion of the DUT screen.

Arguments:

pattern	Text or pattern to find. Search all text with pattern "" (default).
regex	Use pattern as a regexp. [True False (default)].
language	OCR language e.g. "English" (default), "Finnish".
min_score	Minimum score (confidence value). 0.0 - 1.0. Default is 0.8, value over 0.6 means the sequences are close matches.
case_sensitive	Should the comparison be done case sensitive or not. [True (default) False]
crop_left	Left coordinate for cropping rectangle. If None then 0 is used.
crop_upper	Upper coordinate for cropping rectangle. If None then 0 is used.
crop_right	Right coordinate for cropping rectangle. If None then maximum value is used.
crop_lower	Lower coordinate for cropping rectangle. If None then maximum value is used.
crop_unit	Unit of crop coordinates One of "per", "pix" or "mm".
exposure	Exposure in seconds. If not set, uses last exposure used.
gain	Gain value. If not set, uses last gain value used.
detector	Name of text detector to use.
offset_x	Take the picture with an offset in x from the DUT display center. (default is 0)
offset_y	Take the picture with an offset in y from the DUT display center. (default is 0)
filter	Name of filter to apply to the image before text search. None to use no filtering (default).
camera_id	Name of the camera that is being used. (default is Camera1)
parameters	Additional parameters for the OCR engine.

Returns:

Dictionary with keys "success", "results" and "screenshot". Response body: success -- Always True results -- Array of Result objects screenshot -- Name of the screenshot The results array is ordered in page order i.e. text found from left to right and top to bottom. Note that this means that the first item might not have the highest score. Result object (dictionary): score -- Match score [0.0 .. 1.0] topLeftX_px -- Bounding box top left x coordinate in pixels topLeftY_px -- Bounding box top left x coordinate in pixels bottomRightX_px -- Bounding box bottom right x coordinate in pixels bottomRightY_px -- Bounding box bottom right y coordinate in pixels centerX_px -- Bounding box center x coordinate in pixels centerY_px -- Bounding box center y coordinate in pixels topLeftX -- Bounding box top left x coordinate in mm topLeftY -- Bounding box top left x coordinate in mm bottomRightX -- Bounding box bottom right x coordinate in mm bottomRightY -- Bounding box bottom right y coordinate in mm centerX -- Bounding box center x coordinate in mm centerY -- Bounding box center y coordinate in mm

Method: `filter_lines`

Description:

Filter list of (x1, y1, x2, y2) lines with given region and margin. The filter will cut lines to pieces that fit inside the region with given margin. One given line can result to none or several lines.

Arguments:

lines	List of (x1, y1, x2, y2) lines, in millimeters.
region	Name of the filter region.
margin	Margin inwards the region, millimeters.

Returns:

List of list of (x1, y1, x2, y2) lines (each given line results to a list of lines).

Method: `filter_points`

Description:

Filter a list of points that are inside of DUT shape, given region and margin.

Arguments:

points	List of (x, y) points, millimeters.
region	Name of the region.
margin	Margin inwards the given region, millimeters.

Returns:

Filtered list of (x, y) points.

Method: `move`

Description:

Moves in to given DUT position via straight path. DEPRECATED: Added for client compatibility.

Arguments:

x	Target x coordinate on DUT.
y	Target y coordinate on DUT.
z	Target z coordinate on DUT.
tilt	Tilt angle in DUT frame (default: 0).
azimuth	Azimuth angle in DUT frame (default: 0).
robot_name	Name of robot to move.

Method: `show_image`

Description:

Shows image on DUT screen. If image is bytes object, use: `image = base64.decodebytes(image.encode("ascii"))`

Arguments:

image	base64 encoded data. None will empty the screen
-------	---

Returns:

"ok" / error

Method: `set_svg_data`

Description:

Sets SVG file for the DUT

Arguments:

base64_data	base64 encoded svg image, or None if you want to remove the current SVG.
-------------	--

Returns:

"ok" / error

Method: `circle`

Description:

Performs a circle movement with given parameters.

Arguments:

x	Circle center x coordinate on DUT.
y	Circle center y coordinate on DUT.
r	Circle radius.
n	How many circles should be moved. Can be floating point.
angle	Start angle in degrees. For 0 angle, start x is x+r and start y is y.
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
tilt	Tilt angle in DUT frame (default: 0).
azimuth	Azimuth angle in DUT frame (default: 0).
clearance	Coordinate z on dut when moving in circle (default: 0).
clockwise	True if moving clockwise, false to move counter clockwise (default: false).
separation	Separation during circle. If None, then default separation is used.
tool_name	Name of tool to perform circle with. One of 'tool1', 'tool2', 'both' or None. None is the same as 'tool1'.

Method: compass

Description:

Compass movement. Primary finger (the left finger) stays at x, y position while the other finger rotates around it. Rotation starts at azimuth angle azimuth1 and ends at azimuth angle azimuth2. Rotation will be done to shortest route direction.

Arguments:

x	Target x coordinate on DUT.
y	Target y coordinate on DUT.
azimuth1	Start azimuth angle.
azimuth2	End azimuth angle.
separation	Distance between fingers during the gesture
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
clearance	Distance from DUT surface during gesture.
kinematic_name	Name of kinematic to perform the gesture with

Returns:

"ok" / error

Method: compass_tap

Description:

Compass movement with tapping. Primary finger (the left finger) stays at x, y position while the other finger rotates around it. Rotation starts at azimuth angle azimuth1 and ends at azimuth angle azimuth2. Rotation will be done to shortest route direction. Tapping is done with selected finger. (moving finger by default)

Arguments:

x	Target x coordinate on DUT.
y	Target y coordinate on DUT.
azimuth1	Start azimuth angle.
azimuth2	End azimuth angle.
separation	Distance between fingers during the gesture.
tap_azimuth_step	Angle in degrees between taps.

z	Target z coordinate on DUT when hovering before and after gesture and in-between taps (default: DUT's base_distance).
tap_with_stationary_finger	Stationary or moving finger does the tapping.
clearance	Distance from DUT surface during gesture.

Returns:

"ok" / error

Method: double_tap

Description:

Performs a double tap with given parameters.

Arguments:

x	Target x coordinate on DUT.
y	Target y coordinate on DUT.
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
tilt	Tilt angle in DUT frame (default: 0).
azimuth	Azimuth angle in DUT frame (default: 0).
clearance	Target z coordinate on DUT when tapping (default: 0).
duration	How long to keep finger down in seconds (default: 0s).
interval	How long to pause between taps in seconds (default: 0s).
separation	Separation during tap. If None, then default separation is used.
tool_name	Name of tool to perform tap with. One of 'tool1', 'tool2', 'both' or None. None is the same as 'tool1'.

Method: drag

Description:

Performs a drag with given parameters.

Arguments:

x1	Start x coordinate on DUT.
y1	Start y coordinate on DUT.
x2	End x coordinate on DUT.
y2	End y coordinate on DUT.
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
tilt1	Start tilt angle in DUT frame.
tilt2	End tilt angle in DUT frame.
azimuth1	Start azimuth angle in DUT frame.
azimuth2	End azimuth angle in DUT frame.
clearance	Z coordinate on DUT when running drag (default: 0)
predelay	Delay between touchdown and move in seconds.
postdelay	Delay between the end of movement and touchup in seconds.
separation	Separation during drag. If None, then default separation is used.
tool_name	Name of tool to perform drag with. One of 'tool1', 'tool2', 'both' or None. None is the same as 'tool1'.

Method: drag_force

Description:

Performs a drag with force with given parameters.

If given force parameter is a list of forces, the applied force is interpolated over the listed values during the drag movement.

Force can be applied with tool1, tool2 or with both simultaneously. Note that the tool that is used must have a valid force

calibration table in the configuration. Otherwise exception is raised. In case both tools are used, the given force is per tool so that force=100 & tool_name="both" will apply 200 gF on the target.

Arguments:

x1	Start x coordinate on DUT.
y1	Start y coordinate on DUT.
x2	End x coordinate on DUT.
y2	End y coordinate on DUT.
force	Grams of force to apply when running on DUT surface. May also be a list of force values.
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
tilt1	Start tilt angle in DUT frame.
tilt2	End tilt angle in DUT frame.
azimuth1	Start azimuth angle in DUT frame.
azimuth2	End azimuth angle in DUT frame.
separation	Separation during drag force. If None, then default separation is used.
tool_name	Name of tool to perform drag force with. One of 'tool1', 'tool2', 'both' or None. None is the same as 'tool1'.
force2	Similar as force but applies for the second finger when tool_name equals "both".

Method: drumroll

Description:

Taps tap_count times with two fingers, one finger at a time, starting with finger 1 (left finger). Tapping is done with given azimuth angle and finger separation. Tapping is done tap_duration seconds, to which period the tap_count number of taps is layed out evenly.

Arguments:

x	Target x coordinate on DUT.
y	Target y coordinate on DUT.
azimuth	Azimuth angle during the gesture.
separation	Separation between the fingers during the gesture, millimeters.
tap_count	Number of taps to perform.
tap_duration	Duration of all taps together, seconds.
clearance	Distance from DUT surface during gesture.

Returns:

"ok" / error

Method: fast_swipe

Description:

Performs a fast swipe: - Azimuth is first rotated so that synchro tool is parallel to the swipe direction - While swiping with main XY axis, separation axis is moved to gain additional speed

The fast swipe speed can be at most $2 * \min(\text{max_xy_speed}, \text{max_separation_speed})$. The speed is also limited by the swipe length and maximum separation change. TODO: Need more detailed description of limitations.

Arguments:

x1	Swipe start x coordinate on DUT.
y1	Swipe start y coordinate on DUT.

x2	Swipe end x coordinate on DUT.
y2	Swipe end y coordinate on DUT.
separation1	Swipe start separation.
separation2	Swipe end separation.
speed	Fast swipe speed.
acceleration	Fast swipe acceleration.
tilt1	Fast swipe start tile angle.
tilt2	Fast swipe end tile angle.
clearance	(optional) distance from DUT surface during movement
radius	Swipe radius.

Returns:

"ok" / error

Method: `jump`

Description:

Performs a jump with given parameters. In case jump_height is not given, robot jumps to maximum height along robot z axis.

Arguments:

x	Target x coordinate on DUT.
y	Target y coordinate on DUT.
z	Target z coordinate on DUT.
jump_height	Height of the jump from DUT surface (default: jump to robot maximum height).

Method: `line_tap`

Description:

Moves the robot along a line between x1, y1 and x2, y2 and taps the surface with primary finger at given distances relative to the x1, y1 starting position.

Arguments:

x1	Line start x, millimeters.
y1	Line start y, millimeters.
x2	Line end x, millimeters.
y2	Line end y, millimeters.
tap_distances	List of tap locations as in distances from the beginning of the line, millimeters.
separation	Distance between finger centers, millimeters. If not defined then default distance is used.
azimuth	Azimuth angle to use during the line.
z	Target z coordinate on DUT when hovering before and after gesture and in-between taps. (default: DUT's base_distance).
clearance	(optional) Distance from DUT surface during movement.

Returns:

"ok" / error

Method: `multi_tap`

Description:

Performs multiple tap gestures in DUT context according to given points. Start and end of multi-tap sequence is the base distance of the DUT.

Arguments:

points	List of TnTDUTPoint objects indicating where to tap. Z coordinates of the points are ignored and lift and clearance are used for tap movement.
lift	Distance of how high the effector is raised from the DUT between the taps.
clearance	Z coordinate on DUT on tap down (default: 0).

Method: path

Description:

Performs path movement through given points.

Arguments:

points	List of points to go through.
clearance	Clearance added to z value of each point.
separation	Separation during path. If None, then default separation is used.
tool_name	Name of tool to perform path with. One of 'tool1', 'tool2', 'both' or None. None is the same as 'tool1'.

Method: pinch

Description:

Performs a pinch gesture in DUT context.

Arguments:

x	Target x coordinate on DUT. Target is the middle position between fingers.
y	Target y coordinate on DUT. Target is the middle position between fingers.
d1	Distance between fingers at the beginning.
d2	Distance between fingers at the end.
azimuth	Azimuth angle during the pinch.
z	Overrides base distance.
clearance	Distance from DUT surface during gesture.

Returns:

"ok" / error

Method: press

Description:

Performs a press gesture in DUT context.

Force can be applied with tool1, tool2 or with both simultaneously. Note that the tool that is used must have a valid force calibration table in the configuration. Otherwise exception is raised. In case both tools are used, the given force is per tool so that force=100 & tool_name="both" will apply 200 gF on the target.

Arguments:

x	Target x coordinate on DUT.
y	Target y coordinate on DUT.
force	Force in grams, to be activated after moving to lower position.
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
tilt	Tilt angle in DUT frame (default: 0).
azimuth	Azimuth angle in DUT frame (default: 0).
duration	How long to keep specified force active in seconds (default: 0s).

press_depth	Distance from DUT surface during press, negative values being below/through DUT surface. Tip will be pressed to the desired depth if the force limit is not reached before that. If the force limit is reached before desired depth, the movement will stop there. (default: -1mm).
separation	Separation during press. If None, then current separation is used.
tool_name	Name of tool to perform press with. One of 'tool1', 'tool2', 'both' or None. None is the same as 'tool1'.
force2	Force in grams, to be activated after moving to lower position for 2nd voice coil.

Returns:

"ok" / error

Method: rotate

Description:

Rotate movement: - Middle point of the fingers is moved to (x, y) - Both fingers are lowered to touch the surface - Azimuth axis is rotated from azimuth1 to azimuth2

Arguments:

x	Target x coordinate on DUT. Target is the middle position between fingers.
y	Target y coordinate on DUT. Target is the middle position between fingers.
azimuth1	Start azimuth angle.
azimuth2	End azimuth angle.
separation	Distance between fingers during the gesture
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
clearance	Distance from DUT surface during gesture.

Returns:

"ok" / error

Method: spin_tap

Description:

Performs a spinning tap with given parameters.

Arguments:

x	Target x coordinate on DUT.
y	Target y coordinate on DUT.
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
tilt	Tilt angle in DUT frame (default: 0).
azimuth1	Azimuth angle at start of gesture in DUT frame (default: 0).
azimuth2	Azimuth angle at end of gesture in DUT frame (default: 0)
clearance	Target z coordinate on DUT when tapping (default: 0).
duration	How long to keep finger down in seconds (default: 0s).
spin_at_contact	True: rotation from azimuth1 to azimuth2 happens only when finger is at lowest position. False: Rotation from azimuth1 to azimuth2 happens parallel with Z-movement.

Method: swipe

Description:

Performs a swipe with given parameters. Robot accelerates and decelerates along an arc of given radius before and after touching the DUT.

Arguments:

x1	Swipe start x coordinate on DUT.
y1	Swipe start y coordinate on DUT.
x2	Swipe end x coordinate on DUT.
y2	Swipe end y coordinate on DUT.
tilt1	Swipe start tilt.
tilt2	Swipe end tilt.
azimuth1	Swipe start azimuth.
azimuth2	Swipe end azimuth.
clearance	(optional) distance from DUT surface during movement
radius	Swipe radius.
separation	Separation during swipe. If None, then default separation is used.
tool_name	Name of tool to perform swipe with. One of 'tool1', 'tool2', 'both' or None. None is the same as 'tool1'.

Returns:

"ok" / error

Method: tap

Description:

Performs a tap with given parameters.

Arguments:

x	Target x coordinate on DUT.
y	Target y coordinate on DUT.
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
tilt	Tilt angle in DUT frame (default: 0).
azimuth	Azimuth angle in DUT frame (default: 0).
clearance	(optional) distance from DUT surface during movement
duration	How long to keep finger down in seconds (default: 0s).
separation	Separation during tap. If None, then default separation is used.
tool_name	Name of tool to perform tap with. One of 'tool1', 'tool2', 'both' or None. None is the same as 'tool1'.
kinematic_name	Name of kinematic to perform tap with. One of 'tool1', 'tool2', 'mid', 'synchro' or None. None is the same as 'tool1'.

Returns:

"ok" / error

Method: touch_and_drag

Description:

Perform touch and drag: - Keep touching point (x0, y0) with tip1 - Simultaneously, use tip2 to draw an interpolated line from (x1, y1) to (x2, y2)

Arguments:

x0	Tip1 x coordinate on DUT
y0	Tip1 y coordinate on DUT
x1	Line start x coordinate on DUT
y1	Line start y coordinate on DUT

x2	Line end x coordinate on DUT
y2	Line end y coordinate on DUT
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
clearance	(optional) Distance from DUT surface during movement.
delay	Delay from start of primary finger touch to secondary finger drag.
touch_duration	Duration of primary finger touch. None value means that primary finger touches during entire drag motion.

Returns:

"ok" / error

Method: touch_and_tap

Description:

Performs a gesture where primary finger is touching a location and secondary finger is doing a tapping gesture at another location. You can define the x, y coordinates for both fingers separately.

Arguments:

touch_x	Touching finger x, millimeters.
touch_y	Touching finger y, millimeters.
tap_x	Tapping finger x, millimeters.
tap_y	Tapping finger y, millimeters.
z	Target z coordinate on DUT when hovering before and after gesture and in-between taps (default: DUT's base_distance).
number_of_taps	Number of taps to perform. 1 for single tap, 2 for double tap, ...
tap_predelay	Delay between primary finger touch down and secondary finger first touch down.
tap_duration	Time to wait while the tap finger is down in seconds.
tap_interval	Time interval between the taps, seconds. Only affects number_of_taps >= 2
clearance	Distance from DUT surface during movement.
touch_duration	Duration of primary finger touch in seconds. If None, the finger will touch during the secondary finger tapping motion.

Returns:

"ok" / error

Method: watchdog_tap

Description:

Performs a tap designed for HW level triggering based on when the DUT is touched. Example use case is watchdog measurement.

Arguments:

x	Target x coordinate on DUT.
y	Target y coordinate on DUT.
z	Target z coordinate on DUT when hovering before and after gesture (default: DUT's base_distance).
tilt	Tilt angle in DUT frame (default: 0).
azimuth	Azimuth angle in DUT frame (default: 0).
clearance	(optional) distance from DUT surface during movement
duration	How long to keep finger down in seconds (default: 0s).

trigger_direction	Trigger when touching the DUT. None means that no triggering is done. "TOUCH_START" triggers when tool goes down to start touching the DUT. "TOUCH_END" triggers when tool goes up from DUT detach from it.
-------------------	---

Returns:
"ok" / error

Properties:

base_distance	DUT base distance.
bl	Position of bottom left corner of the DUT.
bottom_left	Bottom left corner. DEPRECATED: Added for client compatibility.
bottom_right	Bottom right corner. This property can't be set. The value is calculated from tl, tr and bl. DEPRECATED: Added for client compatibility.
br	Position of bottom right corner of the DUT. This property can't be set. The value is calculated from tl, tr and bl.
height	DUT height in mm.
orientation	Orientation of the DUT i.e. the basis vectors of DUT's transform matrix. Given as dictionary {'i': x_basis_vector, 'j': y_basis_vector, 'k': z_basis_vector}.
position	Corner positions of the DUT in its relative coordinate system context. Property is in dictionary from {"top_left": top_left, "top_right": top_right, "bottom_left": bottom_left, "bottom_right": bottom_right}. DEPRECATED: Exists for client compatibility.
tl	Position of top left corner of the DUT.
top_left	Top left corner. DEPRECATED: Added for client compatibility.
top_right	Top right corner. DEPRECATED: Added for client compatibility.
tr	Position of top right corner of the DUT.
width	DUT width in mm.

6 Module: `tnt_dut_positioning_client`

6.1 Class: `TnTDUTPositioningClient`

Method: `dut_positioning_image`

Description:

Returns DUT positioning image according to input parameters.

Arguments:

<code>width</code>	Image width in pixels.
<code>height</code>	Image height in pixels.
<code>ppmm</code>	Image scaling in pixels per millimeter. Image markers have a fixed diameter of 8 mm, which is scaled to number of pixels using this parameter.

Returns:

Positioning image in PNG-format.

Method: `positioning_image_parameters`

Description:

Returns dictionary of positioning image parameters according to image input parameters.

Arguments:

<code>width</code>	Image width in pixels.
<code>height</code>	Image height in pixels.
<code>ppmm</code>	Image scaling in pixels per millimeter.

Returns:

Dictionary with image parameters.

Method: `add_robot_plane_point`

Description:

Add new plane point for the determination of DUT plane.

Arguments:

<code>point</code>	Point as list [x, y, z].
--------------------	--------------------------

Method: `calculate`

Description:

Calculate the DUT positioning based on positioned blobs and plane points.

Arguments:

None

Returns:

Positioning data.

Method: `center_to_blob_in_image`

Description:

Searches for position markers in the image and centers camera to the first found marker.

Arguments:

dut_name	Name of DUT to position.
camera_exposure	Camera exposure (in seconds) to use in blob detection.
camera_gain	Camera gain to use in blob detection.

Method: clear_plane_points

Description:

Clear plane points that have been added previously.

Arguments:

None

Method: locate_next_blob

Description:

Searches for the next positioning marker in the sequence.

Arguments:

None

Returns:

ID of detected marker.

Method: start

Description:

Start DUT positioning process.

Arguments:

dut_name	Name of DUT to position.
camera_exposure	Camera exposure (in seconds) to use in blob detection.
camera_gain	Camera gain to use in blob detection.
position_image_params	Dictionary containing positioning image parameters. NOTE: The image parameters must match the shown image on the DUT screen. If show_positioning_image is True, this is handled automatically. However, if show_positioning_image is False the user manually sets the image on the DUT screen. In this case the user must make sure the passed parameters correspond to the image being showed.
show_positioning_image	If true, positioning image is sent to DUT (via DUTServer connection)

Method: start_xyz_positioning

Description:

Start complete DUT positioning process which includes sub-steps of surface probing. It is assumed the DUT is roughly horizontal and not inclined significantly wrt the robot tooling plate. Before calling this method the robot should be at a safe z-height to start centering the camera on found markers.

Arguments:

dut_name	Name of DUT to position.
camera_name	Name of positioning camera.
camera_exposure	Camera exposure to use in blob detection.
camera_gain	Camera gain to use in blob detection.
display_ppmm	Screen ppmm of positioned DUT.

position_image_params	Dictionary containing positioning image parameters. NOTE: The image parameters must match the shown image on the DUT screen. If show_positioning_image is True, this is handled automatically. However, if show_positioning_image is False the user manually sets the image on the DUT screen. In this case the user must make sure the passed parameters correspond to the image being showed.
n_markers	Number of markers to use in positioning.
show_positioning_image	If true, positioning image is sent to DUT (via DUTServer connection)

7 Module: `tnt_force_calibrator_client`

7.1 Class: `TnTForceCalibratorClient`

Node for voice coil calibration functionality

Method: `calibrate`

Description:
Perform force calibration synchronously.

Arguments:

<code>axis_name</code>	Name of axis to calibrate for force. None to use the default.
<code>press_duration</code>	Press duration during calibration. If None, then default configured value is used.

Returns:
Dict which contains finished force calibration.

Method: `save_calibration`

Description:
Saves the corresponding calibration data to the server configuration file

Arguments:

<code>calibration_id</code>	Calibration uuid
-----------------------------	------------------

Returns:
None

8 Module: `tnt_futek_client`

8.1 Class: `TnTFutekClient`

Method: `forcevalue`

Description:
Returns force sensor reading in grams

Arguments:
None

Method: `tare`

Description:
Tare sensor based on given parameters.

Arguments:

<code>window_size</code>	How many samples to take when accounting if force is stabilized
<code>gram_diff</code>	How many gram difference is allowed for samples
<code>timeout_s</code>	How many seconds to try before giving up

9 Module: `tnt_hsup_client`

9.1 Class: `TnTHsupWatchdogClient`

Class for performing Human Simulated User Performance (HSUP) analysis.

Method: `get_results`

Description:

Return results of the analysis.

Arguments:

<code>timeout</code>	With timeout None, the function will block until results are available. If timeout is a positive number, the function waits for the specified number of seconds for the results to be ready. If results are not available after the specified timeout value, an error is returned.
----------------------	--

Returns:

Analysis results. If no analysis results exist, failure status is returned.

Method: `start`

Description:

Starts measurement sequence: analysis and storage processes are started up, camera settings are set and validated and camera capture is started.

Arguments:

<code>settings_path</code>	Path to measurement and analysis settings file (alternative to individual parameters)
<code>params</code>	Measurement parameters. This is a dictionary of camera and analysis parameters. Common analysis parameters are: <code>timeout</code> : Timeout in seconds for camera capture. <code>n_oversampling</code> : Amount of images to capture per trigger signal and to add up together in the analysis. <code>camera_trigger_mode</code> : Camera capture start is either 'Manual' or 'Automatic' from finger touch. <code>display_backlight_sync</code> : True if camera needs to sync frame capture to rolling backlight

Returns:

Status reply

Method: `get_status`

Description:

Query status of the HSUP analysis. Includes information about storage and analysis process state.

Arguments:

None

Returns:

Dictionary with process statuses, number of images captured and number of images waiting for analysis.

9.2 Class: `TnTHsupSpaClient`

Class for performing Human Simulated User Performance (HSUP) analysis.

Method: `get_results`

Description:

Return results of the analysis.

Arguments:

timeout	With timeout None, the function will block until results are available. If timeout is a positive number, the function waits for the specified number of seconds for the results to be ready. If results are not available after the specified timeout value, an error is returned.
---------	--

Returns:

Analysis results. If no analysis results exist, failure status is returned.

Method: start

Description:

Starts measurement sequence: analysis and storage processes are started up, camera settings are set and validated and camera capture is started.

Arguments:

settings_path	Path to measurement and analysis settings file (alternative to individual parameters)
params	Measurement parameters. This is a dictionary of camera and analysis parameters. Common analysis parameters are: timeout: Timeout in seconds for camera capture. n_oversampling: Amount of images to capture per trigger signal and to add up together in the analysis. camera_trigger_mode: Camera capture start is either 'Manual' or 'Automatic' from finger touch. display_backlight_sync: True if camera needs to sync frame capture to rolling backlight

Returns:

Status reply

Method: get_status

Description:

Query status of the HSUP analysis. Includes information about storage and analysis process state.

Arguments:

None

Returns:

Dictionary with process statuses, number of images captured and number of images waiting for analysis.

9.3 Class: TnTHsupP2IClient

Class for performing Human Simulated User Performance (HSUP) analysis.

Method: get_results

Description:

Return results of the analysis.

Arguments:

timeout	With timeout None, the function will block until results are available. If timeout is a positive number, the function waits for the specified number of seconds for the results to be ready. If results are not available after the specified timeout value, an error is returned.
---------	--

Returns:

Analysis results. If no analysis results exist, failure status is returned.

Method: start

Description:

Starts measurement sequence: analysis and storage processes are started up, camera settings are set and validated and camera

capture is started.

Arguments:

settings_path	Path to measurement and analysis settings file (alternative to individual parameters)
params	Measurement parameters. This is a dictionary of camera and analysis parameters. Common analysis parameters are: timeout: Timeout in seconds for camera capture. n_oversampling: Amount of images to capture per trigger signal and to add up together in the analysis. camera_trigger_mode: Camera capture start is either 'Manual' or 'Automatic' from finger touch. display_backlight_sync: True if camera needs to sync frame capture to rolling backlight

Returns:

Status reply

Method: `get_status`

Description:

Query status of the HSUP analysis. Includes information about storage and analysis process state.

Arguments:

None

Returns:

Dictionary with process statuses, number of images captured and number of images waiting for analysis.

10 Module: `tnt_icon_client`

10.1 Class: `TnTIconClient`

Icon resource holding reference to Halcon Shapemodel file and to reference PNG image.

Method: `png`

Description:
Get icon PNG image.

Arguments:
None

Returns:
PNG image.

Method: `convert`

Description:
Convert given image to icon model. Can also re-convert existing PNG image to update the icon model.

Arguments:

<code>image</code>	PNG image as base64 encoded string or bytes object. If None, then existing PNG is converted.
<code>parameters</code>	Optional parameters for shape model creation to override default parameters. Example: with <code>open("icon_image.png", "rb")</code> as file: <code>data = file.read()</code> <code>icon_client.convert(data)</code>

11 Module: `tnt_image_client`

11.1 Class: `TnTImageClient`

Image object that stores image pixels as rectangular array and some metadata such as ppm value that was used in case image was captured with a camera. Image is a node meaning that it can also have a homogeneous transform with respect to parent node. Operations such as cropping maintain the validity of this transformation. Note that only image pixel data is saved so the metadata and transformation are lost on server restart.

Method: `find_objects`

Description:

Find an object from the image.

Arguments:

<code>filename</code>	Name of the icon. This is the same as the icon filename without extension.
<code>min_score</code>	Minimum accepted confidence score of result [0.0 .. 1.0] (default 0.8).
<code>detector</code>	Name of detector to be used in object recognition.
<code>parameters</code>	Optional detection parameters to override default values.

Returns:

Dictionary with keys: "success", "results". Response body: success -- Always True results -- Array of Result objects Result object (dictionary): score -- Match score [0.0 .. 1.0] topLeftX_px -- Bounding box top left x coordinate in pixels topLeftY_px -- Bounding box top left y coordinate in pixels bottomRightX_px -- Bounding box bottom right x coordinate in pixels bottomRightY_px -- Bounding box bottom right y coordinate in pixels centerX_px -- Bounding box center x coordinate in pixels centerY_px -- Bounding box center y coordinate in pixels topLeft_mm -- Bounding box top left x coordinate in mm topLeftY_mm -- Bounding box top left y coordinate in mm bottomRightX_mm -- Bounding box bottom right x coordinate in mm bottomRightY_mm -- Bounding box bottom right y coordinate in mm centerX_mm -- Bounding box center x coordinate in mm centerY_mm -- Bounding box center y coordinate in mm shape -- Name of the shape file scale -- Detected icon scale angle -- Detected icon angle Note: The bounding box mm coordinates are only calculated in case image object is a transform child of e.g. a DUT or a camera. Otherwise the coordinates don't exist in the result dictionary.

Method: `jpeg`

Description:

Get image as JPEG formatted bytearray.

Arguments:

None

Method: `png`

Description:

Get image as PNG formatted bytearray.

Convert to Numpy array using OpenCV: `nparr = np.fromstring(png, np.uint8) img_np = cv2.imdecode(nparr, cv2.IMREAD_COLOR)`

Arguments:

None

Method: `search_text`

Description:

Search text pattern from the image.

Arguments:

pattern	Text or pattern to find. Search all text with pattern "" (default).
regex	Use pattern as a regexp. [True False (default)].
language	OCR language e.g. "English" (default), "Finnish".
min_score	Minimum score (confidence value). 0.0 - 1.0. Default is 0.8, value over 0.6 means the sequences are close matches.
case_sensitive	Should the comparison be done case sensitive or not. [True (default) False]
detector	Name of text detector to use.
parameters	Additional parameters for the OCR engine.

Returns:

Dictionary with keys "success", and "results". Response body: success -- Always True results -- Array of Result objects The results array is ordered in page order i.e. text found from left to right and top to bottom. Note that this means that the first item might not have the highest score. Result object (dictionary): score -- Match score [0.0 .. 1.0] topLeftX_px -- Bounding box top left x coordinate in pixels topLeftY_px -- Bounding box top left y coordinate in pixels bottomRightX_px -- Bounding box bottom right x coordinate in pixels bottomRightY_px -- Bounding box bottom right y coordinate in pixels centerX_px -- Bounding box center x coordinate in pixels centerY_px -- Bounding box center y coordinate in pixels topLeftX_mm -- Bounding box top left x coordinate in mm topLeftY_mm -- Bounding box top left y coordinate in mm bottomRightX_mm -- Bounding box bottom right x coordinate in mm bottomRightY_mm -- Bounding box bottom right y coordinate in mm centerX_mm -- Bounding box center x coordinate in mm centerY_mm -- Bounding box center y coordinate in mm Note: The bounding box mm coordinates are only calculated in case image object is a transform child of e.g. a DUT or a camera. Otherwise the coordinates don't exist in the result dictionary.

Method: `transform_point`

Description:

Transform 2D point on the image to parent context. In case the parent is DUT, this transforms image pixel coordinates to DUT coordinates which are in mm

Arguments:

x	Image pixel x-coordinate.
y	Image pixel y-coordinate.

Returns:

Point in parent context as dict {"x": x, "y": y}.

Method: `convert_to_gray_scale`

Description:

Convert image to gray scale. Operation is applied to the image in memory. Change is not applied to the image file.

Arguments:

None

Method: `crop`

Description:

Crop image. Cropping is applied to the image in memory. Change is not applied to the image file.

Arguments:

crop_left	Left coordinate for cropping rectangle.
crop_upper	Upper coordinate for cropping rectangle.
crop_right	Right coordinate for cropping rectangle.
crop_lower	Lower coordinate for cropping rectangle.
crop_unit	Unit of crop coordinates. One of "per", "mm", or "pix".

Method: `filter`

Description:

Filter image by using Python script. The scripts are located under "data/image_filters" and the filter names are specified by attribute FILTER_NAME within those files. Note: filter should not apply a spatial transform to the image or resize the image.

Otherwise transformation of pixel coordinates to mm coordinates in e.g. `find_objects()` becomes invalid.

Arguments:

<code>filter_name</code>	Name of filter specified in the script file.
<code>parameters</code>	Parameter dict to pass to the filter function.

Method: `invert`

Description:

Invert image colors. Operation is applied to the image in memory. Change is not applied to the image file.

Arguments:

None

Method: `resize`

Description:

Resizes the image. At least one parameter should have a value. If factor is given width and height should be empty. Width and height can be given at same time.

Arguments:

<code>width</code>	New width.
<code>height</code>	New height.
<code>factor</code>	Scale factor for the image.

Method: `save_image`

Description:

Save image to file. Image object name is used as filename. Note that existing image file will be replaced.

Arguments:

None

Method: `set_jpeg`

Description:

Set image data as JPEG.

Arguments:

<code>image</code>	JPEG image as base64 encoded string. Can also be bytes object (will be automatically converted to base64). Example: with <code>open("image.jpeg", "rb")</code> as file: <code>data = file.read()</code> <code>image_client.set_jpeg(data)</code>
--------------------	--

Method: `set_png`

Description:

Set image data as PNG.

Arguments:

<code>image</code>	PNG image as base64 encoded string. Can also be bytes object (will be automatically converted to base64). Example: with <code>open("image.png", "rb")</code> as file: <code>data = file.read()</code> <code>image_client.set_png(data)</code>
--------------------	---

Properties:

<code>height</code>	Image height in pixels.
<code>width</code>	Image width in pixels.

12 Module: `tnt_microphone_client`

12.1 Class: `TnTMicrophoneClient`

Method: `device_default_sample_rate`

Description:
The default sample rate of the microphone

Arguments:
None

Returns:
default sample rate

Method: `get_latest_recording`

Description:
Fetch the latest recording ----- To save audio to a file one can use the following python commands: `f = open("test.wav", 'wb') f.write(microphone.record_audio(3)) f.close()` -----

Arguments:
None

Returns:
.wav formatted bytes

Method: `list_recording_devices`

Description:
List all the recording devices found in the system

Arguments:
None

Returns:
Names in a list

Method: `record_audio`

Description:
Records audio for the given duration in seconds. ----- To save audio to a file one can use the following python commands: `f = open("test.wav", 'wb') f.write(microphone.record_audio(3)) f.close()` -----

Arguments:

<code>record_duration</code>	duration of the record (s)
------------------------------	----------------------------

Returns:
.wav formatted bytes

Properties:

<code>chunk_size</code>	The <code>chunk_size</code> size of sample processing.
-------------------------	--

device_name	Name of the microphone device. This is used to choose the correct input device from all the devices seen by the system.
margin	Amount of samples ignored from the beginning of the record to avoid microphone startup noise interference.
rate	Recording data rate (samples/second).
timeout_buffer	Amount of time waited after recording before timeout, in seconds.

13 Module: `tnt_motherboard_client`

13.1 Class: `TnTMotherboardClient`

Method: `set_output_state`

Description:
Set state of certain motherboard output.

Arguments:

<code>name_or_number</code>	Configured alias or number of the output.
<code>state</code>	0 or 1.

Returns:
Request output.

14 Module: `tnt_physical_button_client`

14.1 Class: `TnTPhysicalButtonClient`

TnT™ Compatible Button resource

Properties:

<code>approach_position</code>	Robot position where button can be approached with linear movement.
<code>jump_height</code>	Height from approach position where robot can safely move over the approach position in the button's parent context.
<code>pressed_position</code>	Robot position where the button is pressed down by the robot.

15 Module: tnt_robot_client

15.1 Class: TnTRobotClient

Method: `get_active_finger`

Description:

Get active finger.

Arguments:

None

Returns:

Active finger ID.

Method: `get_attached_tips`

Description:

Get names of tips attached to the robot.

Arguments:

None

Returns:

Dictionary where key is tool name and value is name of tip attached to that tool. If no tip is attached then value is None.

Method: `get_finger_separation`

Description:

Get separation of two fingers in mm.

Arguments:

None

Returns:

Separation distance in mm.

Method: `get_position`

Description:

Returns the current robot position in given context.

Arguments:

context	Name of context where to evaluate the position.
details	Return detailed position info.
kinematic_name	Name of kinematic that corresponds to the position.

Returns:

Dictionary with keys 'position' and 'status'.

Method: `get_speed`

Description:

Returns robot's current speed and acceleration.

Arguments:

None

Returns:

Dictionary with keys 'speed' and 'acceleration'.

Method: `set_active_finger`
Description:

Set active finger. Kinematics are applied to the active finger so that it is possible to command either of the two fingers to specified pose.

Arguments:

<code>finger_id</code>	ID of finger to set active. 0=axial finger, 1=separated finger.
------------------------	---

Method: `change_tip`
Description:

Commands robot to change new tool tip from tip holder. DEPRECATED: This is 2-finger TPPT compatibility and does the same as `put_attach_tip()`.

Arguments:

<code>tip</code>	Name of tip to make the current tip.
<code>finger_id</code>	ID of finger where to change tip to. Ignored if robot has only one tool.
<code>attach_manually</code>	If tip is to be attached manually and not with the tip changer.

Returns:

Name of the tip that was attached as dict {"tip": tip_name}

Method: `detach_tip`
Description:

Detach tip from robot finger if one is attached.

Arguments:

<code>tool_name</code>	Name of tool node where tip is detached from. Must be a child of Mount node.
<code>finger_id</code>	ID of finger.
<code>detach_manually</code>	If tip is to be detached manually and not with the tip changer.

Returns:

Name of the tip that was detached as dict {"tip": tip_name}.

Method: `set_finger_separation`
Description:

Set separation of two fingers in mm. Separation distance is measured from finger axes.

Arguments:

<code>distance</code>	Distance in mm.
<code>kinematic_name</code>	Name of kinematic to use for the motion. If None then currently active kinematic is used.

Returns:

Dictionary with "status" key.

Method: `go_home`
Description:

Commands the robot to go into home position.

Arguments:

None

Method: `move`
Description:

Moves robot into a given location using a linear motion. Coordinates and angles are interpreted in given context. Values tilt and azimuth are taken from Euler angles for global static y and z axes (in selected context) that are applied in order y, z. Tilt is angle around y-axis and azimuth is negative angle around z-axis.

Arguments:

x	Target x coordinate.
y	Target y coordinate.
z	Target z coordinate.
tilt	Euler angle for static y-axis (default: 0) in selected context.
azimuth	Negative Euler angle for static z-axis (default: 0) in selected context.
context	Name of context where coordinates and angles are interpreted.

Method: `move_joint_position`

Description:

Moves robot to a specified joint configuration.

Arguments:

joint_position	Target joint configuration as a dictionary of (axis_name: value) items.
speed	Speed of joint movement. If None, current robot speed is used.
acceleration	Acceleration of joint movement. If None, current robot acceleration is used.

Method: `move_relative`

Description:

Moves robot axes by specified distance using linear motion. Parameters are relative to current position and can hence be negative or positive.

Arguments:

x	Relative x axis movement.
y	Relative y axis movement.
z	Relative z axis movement.
tilt	Relative tilt axis movement.
azimuth	Relative azimuth axis movement.

Method: `press_physical_button`

Description:

Performs a press gesture on the given button.

Arguments:

button_name	The button to press.
duration	How long to keep button pressed in seconds (default: 0s).

Returns:

"ok" / error

Method: `reset_robot_error`

Description:

Resets robot error state.

Arguments:

None

Method: `set_speed`

Description:

Set robot speed and acceleration.

Arguments:

speed	Linear movement speed in mm/s.
acceleration	Robot acceleration in mm/s^2.
override	Not used. DEPRECATED.

16 Module: tnt_speaker_client

16.1 Class: TnTSpeakerClient

Node for playing wav files from /data/audio folder with given device

Method: `list_playback_devices`

Description:

Lists all the found playback devices

Arguments:

None

Returns:

Names in a list

Method: `play_wav_file`

Description:

Play wav file of given filename

Arguments:

filename	name of the audio file
----------	------------------------

Returns:

"ok" for a http response

Properties:

chunk_size	The patch size of sample processing
device_name	Name of the speaker device. This is used to choose the correct output device from all the devices seen by the system.

17 Module: `tnt_surface_probe_client`

17.1 Class: `TnTSurfaceProbeClient`

This class controls a surface probing sequence for the given robot.

Method: `abort`

Description:
Aborts currently running surface probing.

Arguments:
None

Method: `probe_z_surface`

Description:
Starts automatic DUT surface z height probing sequence. Robot will move to negative direction along the robot coordinate system Z-axis in steps. Once the surface touch has been detected, the robot either stays at the found surface location or moves back up. Function will block during the probing sequence.

Arguments:

<code>return_to_start</code>	If True, return to start position when surface is found.
<code>tool_name</code>	Name of the tool to use for surface probing. Otherwise move effective position to found surface.

Returns:
Detected surface position.

18 Module: tnt_tip_client

18.1 Class: TnTTipClient

TnT™ Compatible tip resource Tip can be parented to a Tool node.

Properties:

diameter	Diameter of the tip.
first_finger_offset	Distance from the middle of multifinger tip to the first finger.
is_multifinger	Is tip multifinger.
length	Length of the tip.
model	Tip model ("Standard", "Multifinger").
num_tips	Number of tips in multifinger.
separation	Separation of two-finger tool required to pick multifinger.
slot_in	Tip's slot-in position in workspace context. In this position tip is fixed to a rack.
slot_out	Tip's slot-out position in workspace context. In this position tip is free from a rack. When robot attaches or detaches a tip, it will first move over slot-out position.
tip_distance	Axial distance of adjacent tips in multifinger.